



PDF version

SBE Manual V7.5

[Start](#) | [Queues](#) | [Data Folders](#) | [Archive](#) | [Setup](#) | [Submit](#)
[Associated Files](#) | [Other Add-ons](#) | [Related Batch Processes](#) | [Special Forms](#)

Setup

- ▶ Core Components
- ▶ Archive
- ▶ Settings
- ▶ Filters
- ▶ Run

Data Input

- ▶ File System
- ▶ LP (Line Printer)
- ▶ Named Pipes

Delivery

- ▶ Print Servers
- ▶ Printer Licensing
- ▶ **Email**
- ▶ Application
- ▶ Delivery Monitor

Email

FTSpooler offers two e-mailing methods: Simple Mail Transfer Protocol (SMTP) and Microsoft® Outlook/Exchange (MAPI).

To configure the SMTP connection:

- Enter the full domain name of the SMTP server in the **Host** textbox.
- Choose a login type from the **Login** drop down menu.
- For login options other than *None*, enter the **User** and **Password** to be used by FTSpooler to log into the SMTP server when sending email.
- Choose an encoding type from the **Encoding** drop down menu.
- Enter a full email address in the **Default sender** textbox to define the sender details for outgoing email.
- Click the **Save** button.

Note: Microsoft Exchange Version 7 has differences from earlier versions, you will need to check these items in Exchange 7 and set them when installing or transferring to Exchange 7.

Check and modify these in Exchange 7 (this information is offered as a guide only, consult Microsoft documentation):

- In **Authentication Properties** tab enable **Basic Authentication** and disable **Offer Basic authentication only after starting TLS**. TLS is the default for Exchange 7 and is not supported by FormTrap.
- If you intend using an **SMTPFrom** name that is different from the authenticated user, give permission to **Send As** a different address. For details of how to grant this permission, refer to the following Microsoft article:

[http://technet.microsoft.com/en-us/library/aa998291\(EXCHG.80\).aspx](http://technet.microsoft.com/en-us/library/aa998291(EXCHG.80).aspx)

If you do not do this and set SMTPFrom different from the authenticated user, you will get this error:

550 5.7.1 Client does not have permissions to send as this sender

To use Outlook/Exchange, the profile information must be available to FTSpooler. The profile name is mandatory, password is optional and required only if the profile is password-protected.

To configure Outlook/Exchange settings:

- Select the appropriate email profile from the **Logon Profile** list. No profile listed means there is no MAPI profile configured. Create and configure a profile on that machine before continuing.
- Enter the password for that profile.
- Click the **Save** button.

Core components

- Archive
- Settings
- Filters
- Run
- Users

Data input

- File system
- LP (Line printer)
- Named pipes

Delivery

- Print servers
- Printer licensing
- E-mail**
- Applications
- Monitor

SMTP

Host:

Login:

User:

Password:

Encoding:

Default sender:

Outlook / Exchange

Logon Profile:

Password:

E-mail settings are modified, but not saved

[Top](#)

[Disclaimer](#) | [Home](#) | [About Us](#) | [News](#) | [Products](#) | [Customers](#) | [Free Trial](#) | [Contact Us](#) | [Success Stories](#)

Copyright 1995-2011 TCG Information Systems Pty. Ltd. All rights reserved.