FTDesign Manual V7.5

PDF version

Design & Objects

▷ Designing a Static Form

▷ Designing a Dynamic Form

Objetcs

⊞ Creating Objects

▷ Deleting Objects

⊞ Arranging Objects

Page Elements

⊞ Creating Page Elements

▷ Deleting Page Elements

⊟ Arranging Page Elements

   ▷ **Structure Map Pane**

   ▷ Navigating between Page Elements

   ▷ Placement and Visibility

Arranging Page Elements - Structure Map Pane

The Structure Map Pane lists the page elements that have been created and the variables associated with that page element. The Structure Map Pane is located in the left bottom panel of your FTDesign window.

```
⊟ 📄 Base Page
      ⚯ PoNo
      ⚯ BillName
      ⚯ PoRev
      ⚯ PoDate
      ⚯ PrintDate
      ⚯ Duplicate
      ⚯ VendorNo
      ⚯ vend-name
      ⚯ vend-add1
      ⚮ vend-add2
      ⚮ vend-add3
      ⚮ vend-add4
      ⚮ Page No
      ⚮ Next Page No
      ⚮ Previous Page No
      ⚮ Doc page count
      ⚮ Job Page No
      ⚮ Date printed
   ⊞ 🔲 MainHeading
      🔲 Summary
   ⊞ 🟨 FooterComment
   ⊞ 🟨 TaxSummary
   ⊞ 🟨 Detail Line
   ⊞ 🟥 Report header
   ⊞ ⬜ Report footer
   ⊞ ⬜ Page header
   ⊞ ⬜ Page footer
   ⊞ 🟦 Brought forward
   ⊞ 🟦 Carried forward
```

⚮ **Mapped Unlinked variable** - field is not linked to a variable on the form but has been mapped to a field in the data (green broken link).

⚯ **Mapped Linked variable** - field is linked to a variable on the form and is associated with a field in the data (green link).

⚮ **Unmapped Unlinked Variable** - field is defined but not linked to a variable on the form nor mapped to a field in the data (grey broken link).

⚭ **Unmapped Linked Variable** - field is linked to a variable on the form but is not associated with a field in the data (grey link). This condition is flagged as an error when trying to preview a form or build a project. You must link all form variables to data prior to building the project or previewing the form.

Top