




Getting Started

[The Design Workspace](#)
[Design Workspace Setup](#)
[Scan from Image Forms](#)
[Response Grid](#)
[Manual Timing Marks](#)
["Fat" Response Shape](#)
[Blind and Other Colors](#)

Manually setting timing marks



You can change the size and spacing of the timing marks by selecting the timing line and clicking the Properties button. This window opens:

Timing marks

Number of timing marks: 41 Units: (300 dpi)

N	Space	Size
1	300.00	21.00
2	60.00	21.00
3	60.00	21.00
4	60.00	21.00
5	60.00	21.00
6	60.00	21.00
7	60.00	21.00
8	60.00	21.00
9	60.00	21.00
10	60.00	21.00
11	150.00	21.00
12	60.00	21.00

Mode: ☒ Edit ☐ Select

Buttons: OK, Cancel, Set sizes..., Set spacing...

Timing marks are always numbered from the top (portrait pages) or left (landscape pages).

In **Edit** mode, you can type in the values for each timing mark, or set an identical universal value for a dimension by clicking either the **Set sizes** or **Set spacing** button. That dimension is applied to all timing lines.

In **Select** mode, you can select a range of values by dragging with the mouse and clicking either **Set sizes** or **Set spacing** to set the dimensions for the selected range.

Timing marks

Number of timing marks: 41 Units: (300 dpi)

N	Space	Size
1	140	23.00
2	60.00	23.00
3	60.00	23.00
4	60.00	23.00
5	60.00	23.00
6	60.00	23.00
7	60.00	23.00
8	60.00	23.00
9	60.00	23.00
10	120	23.00
11	60.00	23.00
12	60.00	23.00

Spacing

50

Buttons: OK, Cancel, Edit, Select, Set sizes..., Set spacing...

This shows space reduction on the first set of timing marks.

Top

[Disclaimer](#) | [Home](#) | [About Us](#) | [News](#)
[Products](#) | [Customer Area](#) | [Free Trial](#) | [Success Stories](#) | [Contact Us](#)
[Copyright © 1995 - 2011 TCG Information Systems Pty. Ltd. All rights reserved.](#)