



PDF version

FTDesign Manual V7.5

Theory & Decisions | Tools & Options | **Printline or Records mode**
 Design & Objects | Masking & Font Change | Projects | Testing & Viewing
 Repaginator | FTSplitDef | Registry Update | Special Forms

Printline or Records Mode

Printline Mode

- ▶ Overview
- ⊕ Input Data

Records Mode


- ▶ Overview
- ⊕ Input Data

Pre-defined Variables

- ▶ Pre-defined Variables

Predefined Fields

FormTrap offers a number of pre-defined variable fields to cover common data requirements. These include the previous, current and next page numbers for the current document, the current system date, and the current number of pages in the entire print job.



Variable	Description
Page No	Current page in the document.
Next Page No	Next page in the document.
Previous Page No	Previous page in the document.
Doc Page count	Total number of pages within the document.
Job Page No	Current page in the print job
Date printed	Date the document is printed.


These variables are calculated by FormTrap at runtime.

[Top](#)


Use pre-defined variable

To use a pre-defined variable:

- Choose **Text** from the **Draw** menu or click the **Text** tool button on the toolbar.
- Click and drag diagonally to add the new text frame.
- release the mouse button and the **Text** dialog box will open.
- On the **Definition** tab, enter sample text into the text box. When creating variable text objects it is best to make the sample text the maximum possible length of the field extracted from the data.
- To link all the sample text to the variable, click on the **Link all...** button.




- To link a section of the sample text to the variable, highlight the relevant text and click the **Link selection...** button.



- In the **Link to field** dialog box, select the pre-defined variable name from the **Field** drop down menu - pre-defined variables are listed in this list.

For more info on Masks see [Masking and Font Change](#).



- Click the **OK** button to link the field to the pre-defined variable.

[Top](#)

[Disclaimer](#) | [Home](#) | [About Us](#) | [News](#) | [Products](#) | [Customers](#) | [Free Trial](#) | [Contact Us](#) | [Success Stories](#)

Copyright © 1995-2011 TCG Information Systems Pty. Ltd. All rights reserved.